

Analyser — User Guide

Version: 1.8 · **Last updated:** May 2026


Analyser is a browser-based tool for inspecting and comparing `.fit` activity files from Garmin devices and other ANT+ sensors. It runs entirely in your browser — no account, no upload, no server. Files are parsed locally.

Table of Contents

1. [Getting Started](#)
2. [The Interface](#)
3. [Device Comparison — Single File](#)
 - [3.1 Device Toggle Bar](#)
 - [3.2 Charts Tab](#)
 - [3.3 Summary Tab](#)
 - [3.4 Mean/Max Tab](#)
 - [3.5 Map Tab](#)
4. [Device Comparison — Multiple Files](#)
 - [4.1 Loading Multiple Files](#)
 - [4.2 Different-Session Files](#)
 - [4.3 Multi-File Device Bar](#)
 - [4.4 Fine-Tuning Timing](#)
5. [Event Comparison](#)
6. [Exporting Data](#)
 - [6.1 Excel Export](#)
 - [6.2 PNG Chart Export](#)
7. [Syncing Device Labels Across Devices](#)
 - [7.1 How Sync Works](#)
 - [7.2 Linking a Second Device](#)
 - [7.3 Sync Status and Errors](#)
 - [7.4 Resetting Your Sync Identity](#)
8. [Reference](#)

1. Getting Started

Open Analyser in your browser. You are greeted with the landing page, which contains a drop zone and a file picker.



To load a file:

- **Drag and drop** one or more `.fit` files onto the drop zone, or
- Click **Choose files** to open the system file picker.

You can load **up to 6 files** at once. Once the files are parsed, you are taken directly to the **Device Comparison** view.

Supported format: `.fit` (Flexible and Interoperable Data Transfer — the standard format exported by Garmin watches, Wahoo computers, and most ANT+ devices). Files from `.tcx` and `.gpx` sources are not currently supported.

2. The Interface

After loading a file, the application has two main views:

View	What it shows
✦ Device Comparison	Sensor streams from one or more files displayed side-by-side on a shared time or distance axis
□ Event Comparison	Two or more runs of the same course aligned by distance, showing where time was gained or lost

The **Device Comparison** view (described in sections 3–4) is the primary view and opens automatically when you load a file.

Navigation

On a **desktop** browser, the two views are accessible from the left sidebar. Click  **Device Comparison** or  **Event Comparison** to switch modes.

On a **tablet or phone**, the sidebar is hidden by default. Tap the  **menu button** in the top-left corner to slide out the navigation drawer. Tap any item or tap outside the drawer to close it. You can also swipe left across the drawer to close it.

On a **phone** (narrow screen), a **bottom navigation bar** appears at the foot of the screen with the same  Device and  Event buttons for quick switching without opening the drawer.

Toolbar Controls

On tablet and phone, the toolbar controls (Device Toggle Bar, Channel Toggle Bar, Fine-tune timing) are hidden behind a collapsible panel. Tap the **Devices & Options** (or **Channels & Options**) button to expand or collapse the controls. On desktop the controls are always visible.

Theme

The **Theme** control is in the bottom of the sidebar (or navigation drawer), between the X-axis toggle and the Smoothing slider.

Option	Behaviour
 Sys (default)	Follows your operating system's dark/light preference
 Lit	Forces the light theme regardless of OS setting
 Drk	Forces the dark theme regardless of OS setting

Your choice is saved in your browser and restored the next time you open Analyser.

3. Device Comparison — Single File

Loading a single file opens the Device Comparison view with all detected sensor streams active.




The view is divided into:

- **Left sidebar** — navigation and file controls
- **Device Toggle Bar** — sensors detected in the file, grouped by channel
- **Tab panel** — Charts, Summary, Mean/Max, and Map tabs

3.1 Device Toggle Bar

The Device Toggle Bar sits at the top of the content area and lists every sensor stream detected in the loaded file.



Key concepts:

- Each **pill** represents one device contributing to a channel (e.g. a Polar H10 contributing Heart Rate).
- **Active** devices (highlighted in blue) are included in all charts and statistics. Click a pill to toggle it on or off.
- Channels with a ♦ indicator have data from two or more devices — these are directly comparable.
- **Multi-metric devices** (devices recording 3+ channels, such as a Garmin watch) appear as a single expandable pill. Click the ▼ arrow to see the individual channels.
- Devices that were connected but recorded no data are shown as dashed, semi-transparent pills and cannot be toggled.

Renaming a device:

Double-click any device pill to rename it. Type the new label and press **Enter** to confirm, or **Escape** to cancel. Labels are saved locally in your browser and are restored automatically the next time you load a file from the same device — this works for all device types, including Garmin watches, Stryd pods, ANT+ sensors, and BLE devices.

3.2 Charts Tab

The Charts tab displays time-series data for every active channel.



Reading the charts:

- Each chart plots one channel (e.g. Heart Rate, Power, Pace).
- The **X axis** is either elapsed time or distance — toggle between them with the **Time / Distance** buttons at the top.
- Multiple devices contributing to the same channel each appear as a separate line.
- **Pace** uses an inverted Y axis — faster pace (lower min/km) appears higher on the chart, which matches the intuition of "going faster". Pace is only shown for running activities; it is suppressed for cycling files where it is not meaningful.

Interacting with the charts:

Action	Effect
Hover	Tooltip shows exact values across all series at that position
Click + drag	Zoom in on a time/distance range
Double-click	Reset zoom
Scroll wheel	Zoom in/out (all charts stay synchronised)

Lap markers appear as faint vertical lines across all charts. Hover a marker to see the lap number and split time.

Per-series statistics:

Below each chart, a compact stats row shows the **minimum**, **average**, and **maximum** for every active device series:

- Each entry is colour-coded with a dot matching the chart line so you can immediately associate the number with the series.
- Pace values are formatted as M:SS. Because pace is an inverted metric (lower min/km = faster), the labels are reversed: **max** shows the fastest pace and **min** shows the slowest, displayed as `max / avg / min`. Numbers still read ascending left-to-right.
- Hover any entry to see the exact sample count and x-axis range it covers.
- **Zoom-aware:** when you zoom into a region, the stats recalculate using only the visible data. Zoom back out (or double-click) to see full-activity stats.


Note: Stats in this row reflect the current smoothing and axis mode (distance or time) and may differ slightly from the Summary tab, which uses the raw unsmoothed data from the original file.

Smoothing:

A smoothing control lets you apply a rolling average to reduce sensor noise. Increase the window (in seconds) to smooth out spikes; set it to 1 s for raw data. Smoothing applies to all channels simultaneously.

3.3 Summary Tab

The Summary tab shows aggregate statistics for every active device and channel.



	Device 3	stryd	stryd	garmin
CHANNEL	AVG / MAX / MIN	AVG / MAX / MIN	AVG / MAX / MIN	AVG / MAX / MIN
Heart Rate	145.5 / 157.0 / 90.0	145.5 / 157.0 / 90.0	145.5 / 157.0 / 90.0	145.5 / 157.0 / 90.0
Power	245.5 / 318.0 / 0.0	245.5 / 318.0 / 0.0	245.5 / 318.0 / 0.0	245.5 / 318.0 / 0.0
Speed	9.1 / 10.3 / 0.0	9.1 / 10.3 / 0.0	9.1 / 10.3 / 0.0	9.1 / 10.3 / 0.0
Cadence	83.0 / 87.0 / 0.0	83.0 / 87.0 / 0.0	83.0 / 87.0 / 0.0	83.0 / 87.0 / 0.0
Stride Length	912.4 / 1139.0 / 480.0	912.4 / 1139.0 / 480.0	912.4 / 1139.0 / 480.0	912.4 / 1139.0 / 480.0
Pace	6.7 / 66.1 / 5.8	6.7 / 66.1 / 5.8	6.7 / 66.1 / 5.8	6.7 / 66.1 / 5.8
Altitude	25.8 / 34.0 / 16.8	25.8 / 34.0 / 16.8	25.8 / 34.0 / 16.8	25.8 / 34.0 / 16.8
Temperature	17.8 / 22.0 / 16.0	17.8 / 22.0 / 16.0	17.8 / 22.0 / 16.0	17.8 / 22.0 / 16.0
Vert. Oscillation	58.7 / 126.2 / 45.0	58.7 / 126.2 / 45.0	58.7 / 126.2 / 45.0	58.7 / 126.2 / 45.0
Ground Contact	304.2 / 716.0 / 276.0	304.2 / 716.0 / 276.0	304.2 / 716.0 / 276.0	304.2 / 716.0 / 276.0


For each channel, the table shows:

Column	Meaning
Device	The sensor that recorded this channel
Avg	Time-weighted average over the active portion of the activity
Max	Peak value recorded
Total	Cumulative value (distance, calories) — shown where applicable

Toggling devices in the Device Toggle Bar updates the Summary table immediately.

3.4 Mean/Max Tab

The Mean/Max tab plots the **best average power** (or other metric) over every possible duration, from one second up to the full activity length.




This is the standard "Critical Power curve" or "Power Duration curve" used in cycling and running:

- The Y axis is the best average power achieved for the duration on the X axis.
- A high, flat curve indicates sustained high output; a steep drop-off indicates strength over short durations but limited endurance.
- When multiple files are loaded, each file produces its own curve — load two sessions to compare fitness progress.


3.5 Map Tab

The Map tab renders the GPS route recorded in the activity.



Tile layers:

A **Map Layer** panel is always visible in the **top-left** corner of the map. Click any layer name to switch the base map:



Layer	Best for
Streets (default)	Road runs, orientating yourself
Satellite	Seeing the actual terrain
Topo	Hilly routes — contour lines visible
Cycling	Bike-specific road markings
Dark	Low-glare, high-contrast viewing

Metric colouring:

Use the **Colour by** dropdown in the **top-right** of the map to shade the route by a metric such as pace, heart rate, or power. The colour gradient runs from blue (low values) to red (high values). A legend appears in the bottom-right showing the value range.

Metric strip chart:

When you select a metric in the **Colour by** dropdown, a strip chart slides in below the map showing that channel's values plotted against **distance**. The strip chart occupies approximately 30% of the map panel height; the map retains the remaining 70%.

- Select **None** in the dropdown to hide the strip chart and return the map to full height.
- On **tablet and phone** the strip chart is collapsed by default — tap the **Metric Chart** ▼ header to expand it.
- A **line / gradient** toggle button in the strip chart header switches between a standard line and a spectral gradient style that matches the map route colouring (single-file only; gradient is disabled when multiple files are loaded).

Bidirectional hover sync:

The map and strip chart are linked in both directions:

- Hover over the **map route** — a crosshair appears on the strip chart at the corresponding distance.
- Hover over the **strip chart** — the position marker on the map moves to the corresponding GPS location on the route.
- Move off either surface to clear the cursor on the other.

Hover interaction (Charts tab):


Hovering over the map route also shows a crosshair on all open Charts-tab charts, letting you pinpoint exactly what your metrics were at a specific GPS location.

4. Device Comparison — Multiple Files

Analyser supports loading up to **6 files simultaneously**, enabling you to compare sensor data across different activities or devices.

4.1 Loading Multiple Files

Select multiple `.fit` files in the file picker (hold Shift or Cmd/Ctrl to select more than one), or drag and drop multiple files onto the drop zone at once.




Note: If the loaded files are from different sessions (start times more than 1 hour apart), Device Comparison will be unavailable — see [section 4.2](#).

4.2 Different-Session Files

Device Comparison is designed for files recorded **during the same session** — for example, two devices worn simultaneously on the same run. Comparing files from completely different activities (different days, different events) produces charts with no meaningful relationship between the data streams.

If you load two or more files whose start times are more than 1 hour apart, Analyser detects this and shows an explanation panel instead of charts:



The **Device Comparison** button in the sidebar also appears greyed-out with a tooltip explaining why it is unavailable.


What to do:

- Click **Switch to Event Comparison →** to use the **Event Comparison** view, which is designed for comparing runs of the same course across different sessions.
- Or remove one of the loaded files (using the **×** button in the sidebar) until the remaining files are from the same session.

Once the remaining files overlap in time (within 1 hour), Device Comparison becomes available again automatically.

4.3 Multi-File Device Bar


In multi-file mode the Device Toggle Bar groups sensors by their source file, with a coloured left-border header for each file.



- Each file gets a unique **colour** (blue, orange, green, purple, ...). All chart series from that file share the same colour.
- Channels with data from two or more files display the **✦** comparable indicator — these are the most valuable channels to compare.
- Use the **Select all / Deselect all** button to quickly show or hide everything.

4.4 Fine-Tuning Timing

Even when files are from the same session, GPS clocks sometimes drift by a few seconds. The **Fine-tune timing** control lets you shift any file forwards or backwards in time to align the traces precisely.



Click the **Fine-tune timing** button (below the Device Toggle Bar, visible in multi-file + time-axis mode) to expand the panel. This control is only relevant when files are from the **same session** — if they are from different sessions, the gate panel is shown instead (see [section 4.2](#)).

Control	Function
–10 / –1 buttons	Shift the file 10 s or 1 s earlier
+1 / +10 buttons	Shift the file 1 s or 10 s later
Numeric input	Type an exact offset in seconds
↺ (Reset)	Return to the GPS-anchored auto-computed offset

The first loaded file is always the **reference** (offset = 0). All other files are shifted relative to it. The offset is shown in the **N adjusted** badge on the toggle button.

Anchor source badge:

Next to each filename in the expanded panel, a small coloured badge shows how Analyser determined the auto alignment for that file:

Badge	Colour	Meaning
Timer	Blue	Aligned to the FIT timer-start event — highest accuracy
GPS move	Blue	Aligned to the first GPS record with movement — typical
GPS fix	Amber	Aligned to the first GPS fix (stationary) — slightly less precise
File start	Grey	No GPS data — aligned by file start time only

Blue badges indicate the best-quality alignment. An amber or grey badge on one file while others are blue may explain a small residual offset — use the nudge buttons to

correct it.

Location mismatch warning:


If Analyser detects that the GPS start points of the loaded files are more than 50 m apart, an amber banner appears at the top of the charts area:

⚠ GPS anchor points are more than 50m apart — these files may be from different locations. Distance comparison may not reflect a shared course.

This can occur if you accidentally loaded files from two different events. Dismiss the banner with the × button, or remove the mismatched file from the sidebar.

5. Event Comparison

The **Event Comparison** view (📊) is designed for comparing multiple runs of the same course — for example, several parkruns on the same route — aligned by **distance** to show exactly where time was gained or lost.



Load two or more `.fit` files, then switch to the Event Comparison tab. The view provides:

- **Time delta plot** — cumulative seconds gained or lost versus distance. Positive values mean you were ahead of the reference run; negative values mean you were behind.
- **Overlaid time-series charts** — pace, speed, heart rate, and power for all files on a shared distance axis.
- **Segment bar chart** — per-kilometre or per-lap time difference, highlighting your best and worst segments.

Tip: Select a reference run using the controls in the sidebar. The time delta is calculated relative to the reference. Try different reference runs to understand where you consistently gain or lose time.

6. Exporting Data

Analyser can export your loaded activity data in two formats: an Excel workbook containing all numeric records, and PNG screenshots of individual charts.

6.1 Excel Export

The **Export Data** button appears in the tab bar on both the Device Comparison and Event Comparison pages. Clicking it builds an `.xlsx` workbook and downloads it immediately — no server involved.

Workbook structure:

Sheet	Contents
Summary	One row per loaded file: filename, sport, start time, total distance (km), and elapsed time
Per-activity sheets	One sheet per file, named after the filename (truncated to 31 characters; duplicates are suffixed (2) , (3) , etc.)

Per-activity sheet columns:

Each activity sheet contains one row per recorded data point with the following columns:

- **Timestamp** — wall-clock date and time of the sample (Excel datetime format)
- **Elapsed (s)** — seconds since the activity start
- **Distance (m)** — cumulative distance in metres
- One column per channel that has at least one non-null value: Heart Rate (bpm), Power (W), Left Power (W), Right Power (W), Cadence (rpm), Speed (km/h), Pace (min/km), Altitude (m), Temperature (°C), Core Temperature (°C), Skin Temperature (°C), Vertical Oscillation (mm), Ground Contact Time (ms), Stride Length (m)

Channels with no data at all in a given file are omitted from that file's sheet. Pace values are formatted as **M:SS strings** (e.g. `5:15`) rather than decimal numbers.

Downloaded filename: `analyser-export-YYYY-MM-DD.xlsx` using your local date.

6.2 PNG Chart Export

Every chart card has a **↓ PNG** download button in its header row. Clicking it downloads a PNG screenshot of that chart at **2x pixel density** for sharp rendering on high-DPI displays.

The PNG uses the chart's current theme (light or dark) as the background, so what you see is what you get.

Downloaded filenames follow the pattern `channel-name-YYYY-MM-DD.png` (e.g. `heart-rate-2026-05-26.png`).

PNG export is available for all four chart types: Time Series, Mean/Max, Time Delta, and Segment Bar.

7. Syncing Device Labels Across Devices

Device labels you create (by double-clicking a sensor pill) are saved in your browser's local storage. The **Sync** feature lets you share those labels across multiple browsers or devices — for example, so your phone and laptop both show "Polar H10" instead of "Device 1".

Sync is **automatic and account-free**. No sign-in is required. Each browser is assigned a private sync identity (a UUID stored in local storage) the first time it loads Analyser.

7.1 How Sync Works

1. On first load, Analyser generates a unique sync identity (UUID) for your browser and pushes your current labels to a cloud key-value store under that identity.
2. On every subsequent load, Analyser pulls the latest labels from the cloud and applies them locally — the cloud is the source of truth.
3. Whenever you rename or remove a device label, the change is automatically pushed to the cloud in the background.
4. All data is keyed by your private UUID. No one else can read or modify your labels without that UUID.

Privacy note: Labels are stored in Upstash Redis and expire automatically after **90 days** of inactivity. No personal information is stored — only the device labels you assign (e.g. "Polar H10", "Assioma Duo") keyed by a randomly generated UUID.

7.2 Linking a Second Device

To share your labels with a second browser or device:

1. Open the **Sync** panel in the sidebar footer (click the  Sync toggle).
2. On the first device:
 - **Scan the QR code** with the second device's camera app — this opens Analyser with the sync identity pre-loaded.
 - Or click  **Copy link** and paste the URL into the second device's browser.
 - Or note the **short sync code** (format: `XXX-XXXXX`, e.g. `E6Y-NXEMF`).
3. On the second device, open Analyser and expand the Sync panel:
 - If you used the QR code or copied link, Analyser automatically pulls labels from the first device's identity — no further action needed.

- If using the short code, type it into the **Link another device** input and press → (or Enter). Analyser resolves the code and pulls labels.

After linking, both devices share the same sync identity and labels stay in sync automatically.

Tip: The QR code and copy-link methods are the most convenient. Use the short code when typing a URL isn't practical.

7.3 Sync Status and Errors

The Sync panel shows a status line:

Status	Meaning
▲ Syncing across devices ✓ · <i>N min ago</i>	Labels synced successfully; time since last sync
Setting up sync...	Initial sync in progress (first visit)
⚠ Sync error — retry	A push or pull failed; click retry to try again

Network errors are non-fatal — if a push fails, your local labels are unchanged and the error is shown in the panel. Analyser will retry automatically on the next label change.

7.4 Resetting Your Sync Identity

If you want to **break the link** between devices (e.g. after lending your laptop to someone):

1. Open the Sync panel and click **Reset sync identity** at the bottom.
2. Confirm when prompted.

A new UUID is generated and your current labels are pushed under the new identity. Devices still using the old identity will no longer receive your label updates.

Note: Resetting does not delete the old identity from the cloud — it simply stops being used. The old data will expire after 90 days of inactivity.

8. Reference

Sync — Quick Reference

Action	How
Open Sync panel	Click  Sync in the sidebar footer
Share labels with another device	QR code, Copy link, or short code
Enter a short code	Type <code>XXX-XXXXX</code> in the Link another device input and press →
Break the link / start fresh	Reset sync identity in the Sync panel
Check last sync time	Status line in the Sync panel

Keyboard Shortcuts

Key	Action
Double-click a chart	Reset zoom
Enter (in rename input)	Confirm device rename
Escape (in rename input)	Cancel device rename
Enter (in offset input)	Confirm time offset

Supported Sensor Types

Sensor	Channels recorded
Heart Rate Monitor (HRM)	Heart Rate
Power Meter (bike)	Power, Left/Right balance
Stryd Running Power	Power, Form Power, Ground Contact Time, Stride Length
Core Body Temperature	Core Temperature, Skin Temperature
Speed/Cadence Sensor	Speed, Cadence
Running Dynamics Pod	Vertical Oscillation, Ground Contact Time, Stride Length
Watch / Primary device	All remaining channels: GPS, Altitude, Speed, Pace, Temperature

File Limits

- **Maximum files per session:** 6
- **Supported format:** `.fit` (ANT/Garmin FIT protocol)
- All parsing happens **locally in your browser** — no data is uploaded to any server.

Troubleshooting

Symptom	Likely cause	Fix
File loads but no charts appear	No sensor data in the file	Check the Device Toggle Bar — all devices may be deselected or no-data
Device Comparison shows "unavailable" panel	Files are from different sessions (start times >1 hour apart)	Use Event Comparison (📅) to compare runs of the same course, or remove the out-of-session file
Two same-session files don't align on the time axis	GPS clock drift between devices	Check the anchor source badges in Fine-tune timing (section 4.4); files with grey or amber badges may need a small manual nudge
Location mismatch warning appears	Files are from different GPS locations (anchors >50 m apart)	Check the files loaded — you may have mixed files from different events; dismiss the banner or remove the mismatched file
Map shows no route	FIT file has no GPS data	Some indoor activities (turbo trainer, treadmill) do not record GPS
Pace chart looks upside-down	Expected — faster pace (lower min/km) is plotted higher	This is correct; it matches the intuition of "going faster = higher on chart"
Device name shows as "Device N"	Device not yet labelled	Double-click the pill to rename it; the label is saved in your browser and restored for future sessions with any device of the same type
Sync panel shows "⚠ Sync error"	Network error or server unavailable	Click retry in the Sync panel; your local labels are unaffected
Short code entry says "Code not found"	Code is invalid, mistyped, or the 90-day TTL has expired	Check the code format (XXX-XXXXX) and re-copy it from the originating device
Labels on second device are out of date	Sync has not triggered yet	Open the Sync panel — pulling happens automatically on load; refresh the page if needed
Sync panel shows "Setting up sync..." for a long time	Connectivity issue on first visit	Check your network; the sync identity is assigned locally first so labels still work offline

Screenshots taken using real activity files: Ayr Parkrun and Zwift/TrainerRoad sessions.